

How to Setup Dynamic Port Forwarding in Remote Desktop Manager



Pop quiz: What are the three common methods of port redirection with SSH?

If your answers are local port forwarding, remote port forwarding and dynamic port forwarding, then...*ding ding ding* You're right! Take a bow and bask in the glory of your Sheldon-like brain.

Local port forwarding, which is the most common option, is used to create a secure connection between a local computer and a remote machine, through which services can be relayed. For example, local port forwarding can be used to bypass a company firewall that would block access to Reddit (how dare they?).



Remote port forwarding is a bit less common. It lets you connect your SSH server to a computer on your company's intranet, which is useful for granting someone on the outside access to an internal web server.

Dynamic port forwarding, which we'll take a closer look at today, is one of the most powerful port forwarding methods, since it lets you bypass a company firewall that would otherwise completely block access to the web. Unlike local and remote port forwarding that only allow interaction with a single port, dynamic port forwarding enables a full range of TCP communication across a range of ports.

You can set up a dynamic port with Putty or with RDM. The added benefit of using RDM is that you can then use your dynamic port to connect with different types of sessions such as SSH, web and RDP.

Here are the steps for setting up dynamic port forwarding in RDM.

Step 1

Create a new SSH Port Forward entry in RDM by clicking **General** on the side menu, and then entering your SSH information in the **SSH Settings** tab. You will need to enter the IP address of the SSH Gateway Server, and the port number of the SSH Gateway Server.

📮 Remote Desktop Manager - PortForv	vard [Default]			
General More Security Permissions Password Management VPN/SSH/Gateway User Interface Information Events Sub Connections Logs Management Tools Advanced	Name Folder Display Credentials General SSH Settin Host Usernan Passwor	PortForward RDP Over SSH Proxy Embedded (tabbed) Default I 192.168.8.25 Port iuseraccount Popular Always ask password Port Always ask password Port Port Port Port Popular Popula	2 <u>p</u>	•
SSH Port Forward				
*** Variables		<u>41</u>	OK	Cancel

In the **General** tab, click on the Plus to create the dynamic link that will be used for every proxy tunnel. The source is 127.0.0.1 and the mode is Dynamic. Remember that the source port must be the same as the one configured in each proxy tunnel entry.

🖵 Remote Desktop Manager - PortForward [Default]							—		×
General More	Name	F	PortForward					⊷	
✓ Security	Folder	1	RDP Over SSH Prox	у		~ •	Off		
Permissions Password Management	Display		Embedded (tabbed)		~				
VPN/SSH/Gateway	Credentials		Default		~				
User Interface Information Events	General	3SH Settings	s Private Key	Advanced	1				
Sub Connections	•4	T 🕺 🖉	<u> </u>						
Logs		Source	Source P	ort	Destination	Destination Port	Mode		
Advanced		127.0.0.1		60000		0	Dynamic		-
◆ SSH Port Forward									
👯 Variables					<u>41</u>		ОК	Cano	cel

Here is the PowerShell script you'll need to enter to create this entry:

```
# Create the SSH Port Forward entry type with Dynamic port
$sshPortForward = New-RDMSession -Name "PortForward" -Type Pc
$sshPortForward.Terminal.Host = "192.168.8.25"
$sshPortForward.Terminal.HostPort = "60025"
$sshPortForward.Terminal.Username = "useraccount"
$sshPortForward.Terminal.PrivateKeyPromptForPassPhrase = $fal
$sshPortForward.Terminal.TCPKeepaliveInterval = 1
$sshPortForward.Terminal.Verbose = $true
$sshPortForward.Terminal.VerbosityLevelMac = 2
$newPortForward = New-Object Devolutions.RemoteDesktopManager
$newPortForward.Mode = "Dynamic"
$newPortForward.Source = "127.0.0.1"
$newPortForward.SourcePort = 60000
$sshPortForward.Terminal.PortForwards = $newPortForward
Set-RDMSession $sshPortForward -Refresh
$pwdSSHPF = ConvertTo-SecureString "123456" -AsPlainText -For
Set-RDMSessionPassword -Session $sshPortForward -Password $pv
Set-RDMSession $sshPortForward -Refresh
```

Create a proxy tunnel entry for each RDP entry, and bind the RDP entry to the proxy tunnel using the VPN settings. Enter the same port number as the SSH port forward entry, and then enter the port number used by the RDP entry. This port number should be unique for every Proxy Tunnel/ RDP entry group. Then enter the IP address of the RDP machine.

Remote Desktop Manager - Proxy Tur	nel 1 [Default]					_		×
General Na More For ✓ Security For Permissions Dia Password Management Dia VPN/SSH/Gateway Cr User Interface G Information G	Name Folder Display Credentials General	ame Proxy Tunnel 1 older RDP Over SSH Proxy ~ isplay Embedded (tabbed) ~ redentials Default ~					2	
Events Sub Connections Logs > Management Tools Advanced	Host Userna Passwo Proxy t	me [ord [127.0.0.1 useraccount SOCKS4	Popular	Port <u>60</u>	<u></u>		
	Local h Remote	ost [host [127.0.0.1 Port <u>61125</u> 4 2 t 10.10.0.25 5					
Proxy Tunnel (HTTP, SOCKS4, SOCKS4A, SOCKS5) Variables	Search	property	Port	3389		ОК	Can	icel

Step 4

In the **General** side menu, click on the **General** tab and enter the port number that you configured in the proxy tunnel (per step 3).

Remote Desktop Manager - RDP Three	ough Proxy 1 [[Default]							-		×	
General	Name		RDP T	RDP Through Proxy 1						5		
 Security Permissions 	Folder		RDP C	ver SSH Pro	a)	×	~		off Off			
Password Management VPN/SSH/Gateway	Credentials		Defau	it		~						
User Interface Information	General	Isplay	Local R	esources	Programs	Experience	Connection	Adva	nced			
Events Sub Connections		Host		127.0.0.1	,			Port	61125	7 🖻		
Logs Management Tools 		RDP type	e	Normal			~					
Advanced		Usernam Domain	e	useraccou	nt							
		Passwor	d	•••••	•		•	Ð 😱				
				Always	Pop ask password	ular I	0	1 hour				
				Store p	Save Pa	ly	×					
Microsoft Remote Desktop (RDP) Configured ~				Open o	console (Admin	n mode)						
🔛 Variables						<i>i</i> A			ОК	Ca	incel	

In the **VPN/SSH/Gateway** side menu, click on the **General** tab and set the following properties: set the VPN **Open** parameter to **Always connect**, and set the **Type** parameter to Proxy Tunnel.

Remote Desktop Manager - RDP Thro	bugh Proxy 1 [Default]	-		×
General More ✔ Security	General Lettings Advanced			
Permissions Received Management	Open 8 Always connect ~		•	
VPN/SSH/Gateway	Close Manually later		•	
Information Jump Host	Type 9 A Proxy Tunnel			
Events Sub Connections	Credentials			
Logs > Management Tools Advanced	Default			
	Installation path Configure			
Microsoft Remote Desktop (RDP) Configured				
Variables	<u> </u>	OK	Ca	ncel

Step 6

Click on the **Settings** tab of the **VPN/SSH/Gateway** side menu. In the **Session** parameter select the proxy tunnel.

Remote Desktop Manager - RDP Thr	bugh Proxy 1 [Default]		×
General More ✔ Security	Genera Settings Idvanced Settings		_
Permissions Password Management	Session RDP Over SSH Proxy\Proxy Tunnel 1	~	
User Interface Information Jump Host	Use dynamic port Force "localhost" Default V		
Events Sub Connections Logs			
> Management Tools Advanced	Other		
	Visibility Default ~		
	Override parent (\$PARENT_HOST\$) Force "allow multiple instances" of VPN		
Microsoft Remote Desktop (RDP) Configured			
	OK OK	Can	cel

Enter the PowerShell code to create the Proxy Tunnel/RDP duo entries. You'll need to put this in a loop in order to create them from your CSV file that contains all of your RDP entries.

```
# For each RDP entry, you need to create a Proxy Tunnel and a
# Create the Proxy Tunnel entry type
$proxyTunnel = New-RDMSession -Name "Proxy Tunnel" -Type Prox
$proxyTunnel.ProxyTunnel.Host = "10.10.0.25"
$proxyTunnel.ProxyTunnel.LocalHost = "127.0.0.1"
$proxyTunnel.ProxyTunnel.LocalPort = "61125"
$proxyTunnel.ProxyTunnel.Port = "3389"
$proxyTunnel.ProxyTunnel.ProxyHost = "127.0.0.1"
$proxyTunnel.ProxyTunnel.ProxyPort = "60000"
$proxyTunnel.ProxyTunnel.ProxyType = "Socks4"
$proxyTunnel.ProxyTunnel.Username = "useraccount"
Set-RDMSession $proxyTunnel -Refresh
$pwdProxy = ConvertTo-SecureString "123456" -AsPlainText -For
Set-RDMSessionPassword -Session $proxyTunnel -Password $pwdPr
Set-RDMSession $proxyTunnel -Refresh
# Create the RDP entry bind to the Proxy Tunnel
$rdp = New-RDMSession -Name "RDP Through Proxy" -Type RDPConf
$rdp.RDP.NetworkLevelAuthentication = $true
$rdp.RDP.Username = "useraccount"
$rdp.VPN.Enabled = $true
$rdp.VPN.Application = "ExistingProxyTunnel"
$rdp.VPN.AutoClose = $false
$rdp.VPN.CloseMode = "Manually"
$rdp.VPN.ExistingSessionID = $proxyTunnel.ID
$rdp.VPN.Mode = "AlwaysConnect"
$rdp.Host = "127.0.0.1"
$rdp.HostPort = "61125"
Set-RDMSession $rdp -Refresh
$pwdRdp = ConvertTo-SecureString "123456" -AsPlainText -Force
Set-RDMSessionPassword -Session $rdp -Password $pwdRdp
Set-RDMSession $rdp -Refresh
```

Important Note

In order for all of this to work, you'll need to open the SSH Port Forward entry and then open the RDP entry. I strongly recommend configuring this set of entries in a test environment before running the whole PowerShell script. It's always better to be safe than sorry!

Save Time and Headaches!

I know there are more steps involved here than many other configuration options in RDM, but spending a few minutes to set up dynamic port forwarding will save you lots of time in the future — and help you avoid some headaches as well!

Please comment below or get in touch with me directly if you have any questions or run into any challenges. Our team will jump on it faster than you can say BA-ZING-A!